

パソコンに「楽にネット」をインストールする方法をご案内いたします。

1 パソコンに
セキュリティーキーを
挿し込みます



2 インストールしたい
ソフトを選択します

このマニュアルでは、
「居宅介護支援」を選択します。
インストール手順はすべてのソフトで共通です。



3 インストール画面が
表示されます
インストールをクリックし
ます



4


「Setup.exe」をクリックします。

ダウンロードのブロックが表示されたらp4「楽にネットのダウンロードできない」をご覧ください。




5

SmartScreenの警告メッセージが表示されたら




6

セキュリティ警告の画面が表示されます
「インストール」をクリックします



楽にネット インストールマニュアル



7 インストールが始まります




警告画面が出たら
「実行」をクリックします



再び
SmartScreen
警告メッセージ
が表示されたら
図のように「実
行」を選びます



8 インストールキーを入力する




9 インストール完了! 「楽にネット」が起動しました ↓デスクトップにアイコンが表示されます




楽にネットが起動せず 下図のメッセージが表示されてしまう場合

- ・PCにセキュリティキーを差しこんでいますか？
- ・セキュリティキーのランプが光っていますか？ 光らない場合は、次のページのドライバーインストールをご覧ください。



❗【楽にネットのダウンロードができない】

🌐をお使いの場合



ダウンロードがブロックされた時は「保存」をクリックします



「ダウンロード」フォルダが開くので「保存」します




「setup.exe」をクリックします。

→保存を押せない場合。ブロックを解除できない場合 →p6へ

保存ボタンが押せない時の対処例




「>」マークをクリックして詳細を開きます




「安全でないファイルをダウンロード」をクリックします

⚠ 警告マークが消えてsetupが開けるようになります



「保存」または「開く」をクリックします




「setup.exeは一般的にダウンロードされていません～」のメッセージが出た場合は手動でダウンロードを進行させます
「…」をクリックします

「保存」をクリックします



「削除」の隣の「V」をクリックします
「保持する」を選びます



「ファイルを開く」がクリックできるようになりました

HASPドライバーのインストール方法

案にネットダウンロードサイトの一番下

【HASP DRIVER(表示されたページ内より「Sentinel HASP/LDK - Windows GUI Run-time Installer」を選択ください。)]を押す。



居宅介護支援	http://download.kai5.jp/DL/kyotaku/publish.htm
訪問介護	http://download.kai5.jp/DL/homonkaigo/publish.htm
通所介護	http://download.kai5.jp/DL/tsusho/publish.htm
福祉用具貸与	http://download.kai5.jp/DL/fukushi/publish.htm
訪問看護	http://download.kai5.jp/DL/kango/publish.htm
居宅療養管理指導	http://download.kai5.jp/DL/kanrishido/publish.htm
地域包括支援センター	http://download.kai5.jp/DL/hokatsu/publish.htm
伝送のみの利用者	http://download.kai5.jp/DL/denso/publish.htm

HASP DRIVER(表示されたページ内より「Sentinel HASP/LDK - Windows GUI Run-time Installer」を選択ください。)]

別サイトに移動し、検索ボックスに【KB0018320】と入れて検索をする。

Notice of Updates to Customer Support Phone Numbers
We are in the process of updating several of our Thales Customer Support phone numbers. Please check the Contact Us page for the latest numbers for your products and region. [Contact Us page](#)

THALES
Support Portal

[Home](#) [Tools](#) [Create Case](#) [Contact Us](#) [Help](#) [Register](#) [Login](#)

Sentinel Services Status Page

Open a Support Case

Drivers and Downloads

Frequently Asked Questions
How do I get support?
Can I create a case?
Support Portal account?

検索結果から【Sentinel LDK Windows GUI Runtime Installer ○○】をクリックする
※○○の部分は数字が入ります。更新のたびに数字が変わり、ここでは「10.14」になります。

Notice of Updates to Customer Support Phone Numbers
We are in the process of updating several of our Thales Customer Support phone numbers. Please check the Contact Us page for the latest numbers for your products and region. [Contact Us page](#)

THALES
Support Portal

Home Tools Create Case Contact Us Help Register Login

KB0018320

Knowledge Center Search Search for knowledge and downloads for Thales products

Refine Search Results

Product

Filter

☐ Sentinel HASP

☐ Sentinel LDK & LDK-EMS

Category

Drivers & Runtime Packages

Article Type

KB0018320

1 results for "KB0018320"

Sort by | Relevance Newest Alphabetical

Showing All Results

 **Sentinel LDK Windows GUI Runtime Installer 10.14**
Number: KB0018320 • Updated: 2025-07-31 • Created: 7y ago

ダウンロードページに移動し【DOW0003347】をクリック

Notice of Updates to Customer Support Phone Numbers
We are in the process of updating several of our Thales Customer Support phone numbers. Please check the Contact Us page for the latest numbers for your products and region. [Contact Us page](#)

THALES
Support Portal

Home Tools Create Case Contact Us Help Register Login

Search

Sentinel LDK Windows GUI Runtime Installer 10.14
KB0018320

Article Details KB0018320

2289058 Views Updated: 2025-07-31 Created: 2018-12-10 ★★★★★

Sentinel® LDK Runtime Environment Installer GUI for Windows
Refer to the Readme file included in the package for details.

Important: Upgrading Sentinel LDK Run-time Environment to version 8.21 or later migrates existing SL-AdminMode and SL-Legacy licenses to a new secure storage. Once this occurs, you cannot downgrade the Run-time Environment to an earlier version. Downgrading the Run-time Environment will make existing SL-AdminMode and SL-Legacy licenses invalid.

Click here to download file: [DOW0003347](#)

Related Product Information

Operating Systems: Windows
Software Versions: 10.14
Components: LDK Runtime

Subscribe to Article

You are not currently logged in.
If you have a Support Portal account, please log in if you wish to subscribe to this article. If you do not have an account, you may subscribe as a public user but will not have access to subscription management features.

[Subscribe](#)

For information on subscriptions, click here.

同意を求められるので同意する ※一番下までスクロールし【I Accept】を押す。

End User License Agreement

SENTINEL LDK PRODUCT END USER LICENSE AGREEMENT

IMPORTANT INFORMATION- PLEASE READ THIS AGREEMENT CAREFULLY BEFORE USING THE CONTENTS OF THE PACKAGE AND/OR BEFORE DOWNLOADING OR INSTALLING THE SOFTWARE PRODUCT. ALL ORDERS FOR AND USE OF THE SENTINEL® LDK PRODUCTS (including without limitation, the Developer's Kit, libraries, utilities, diskettes, CD-ROM, DVD, Sentinel keys, the software component of Sentinel LDK, and the Sentinel LDK Software Protection and Licensing Guide) (hereinafter "Product") SUPPLIED BY THALES DIS CPL USA, Inc., or one of its affiliates, (in each case, referred to hereinafter as "THALES") ARE AND SHALL BE, SUBJECT TO THE TERMS AND CONDITIONS SET FORTH IN THIS AGREEMENT.

BY OPENING THE PACKAGE CONTAINING THE PRODUCTS AND/OR BY DOWNLOADING THE SOFTWARE (as defined hereunder) AND/OR BY INSTALLING THE SOFTWARE ON YOUR COMPUTER AND/OR BY USING THE PRODUCT, YOU ARE ACCEPTING THIS AGREEMENT AND AGREEING TO BE BOUND BY ITS TERMS AND CONDITIONS.

IF YOU DO NOT AGREE TO THIS AGREEMENT OR ARE NOT WILLING TO BE BOUND BY IT, DO NOT OPEN THE PACKAGE AND/OR DOWNLOAD

mchange-commons-java-0.2.15.jar (© 2012-2013 Machinery for Change, Inc.)

c3p0-0.9.5.2.jar (© included in the readme's or equivalent)

aspectjweaver-1.8.10.jar (all required information can be found in the readme's or <https://www.eclipse.org/aspectj/>)


Y. OpenJDK8 is distributed under CDDL License and Gplv2 classpath exception license: <https://oss.oracle.com/licenses/CDDL+GPL-1.1>

DocID 189 Revision 2005-1

✓ I accept

✗ I do not accept

小さい別ページの画面が開き、ファイルがダウンロードされるのでダウンロードが完了したらファイルを開く
※お使いのブラウザによって動作が異なる場合があります。




ダウンロードしたファイルを開き【HASPUserSetup.exe】を開き。

名前	種類	圧縮サイズ	パスワード保護
Sentinel_LDK_Run-time_setup	ファイル フォルダー		

開いたファイルの【HASPUserSetup.exe】を開く。

名前	種類	圧縮サイズ	パスワード保護
Readme_HTML5	ファイル フォルダー		
HASPUserSetup	アプリケーション	46,505 KB	無
Readme	Microsoft Edge HTML Document	1 KB	無

メッセージが出てくるので【全て展開(X)】を押す。
展開先を求められるので、指定先がなければそのまま展開を押す。




ファイルが展開されるので【HASPUserSetup.exe】を開き。

名前	更新日時	種類	サイズ
▼ 今日			
Sentinel_LDK_Run-time_setup	2025/08/14 18:04	ファイル フォルダ	


開いたファイルの【HASPUserSetup.exe】を開く。

名前	更新日時	種類	サイズ
▼ 今日			
HASPUserSetup	2025/08/14 18:04	アプリケーション	47,086 B
Readme	2025/08/14 18:04	Microsoft Edge HTML D...	1 B
Readme_HTML5	2025/08/14 18:04	ファイル フォルダ	


【HASPUserSetup.exe】が起動したら「Next」を押す。



【I accept the license agree ment】にチェックを付けて「Next」を押す。
【Next】を押す。



インストール画面が表示されるので終わるまで待つ。



【Finish】を押して、キーが赤く光れば完了。

